

## HTML Tables

---

HTML tables allow web developers to arrange data into rows and columns

---

### Table Cells

Each table cell is defined by a `<td>` and a `</td>` tag.

`td` stands for table data.

Everything between `<td>` and `</td>` is the content of a table cell.

Example

```
<table>
  <tr>
    <td>Emil</td>
    <td>Tobias</td>
    <td>Linus</td>
  </tr>
</table>
```

---

### Table Rows

Each table row starts with a `<tr>` and ends with a `</tr>` tag.

`tr` stands for table row.

Example

```
<table>
  <tr>
    <td>Emil</td>
    <td>Tobias</td>
    <td>Linus</td>
  </tr>
  <tr>
    <td>16</td>
    <td>14</td>
    <td>10</td>
  </tr>
</table>
```

## **Table Headers**

Sometimes you want your cells to be table header cells. In those cases use the `<th>` tag instead of the `<td>` tag:

`th` stands for table header.

Example

Let the first row be table header cells:

```
<table>
<tr>
<th>Person 1</th>
<th>Person 2</th>
<th>Person 3</th>
</tr>
<tr>
<td>Emil</td>
<td>Tobias</td>
<td>Linus</td>
</tr>
<tr>
<td>16</td>
<td>14</td>
<td>10</td>
</tr>
</table>
```

## **caption**

Definition and Usage

The `<caption>` tag defines a table caption.

The `<caption>` tag must be inserted immediately after the [`<table>`](#) tag.

## **HTML Table - Colspan**

To make a cell span over multiple columns, use the `colspan` attribute:

Example

```

<table>
  <tr>
    <th colspan="2">Name</th>
    <th>Age</th>
  </tr>
  <tr>
    <td>Jill</td>
    <td>Smith</td>
    <td>43</td>
  </tr>
  <tr>
    <td>Eve</td>
    <td>Jackson</td>
    <td>57</td>
  </tr>
</table>

```

## HTML Table - Rowspan

To make a cell span over multiple rows, use the rowspan attribute:

Example

```

<table>
  <tr>
    <th>Name</th>
    <td>Jill</td>
  </tr>
  <tr>
    <th rowspan="2">Phone</th>
    <td>555-1234</td>
  </tr>
  <tr>
    <td>555-8745</td>
  </tr>
</table>

```

## HTML Table - Cell Spacing

Cell spacing is the space between each cell.

By default the space is set to 2 pixels.

To change the space between table cells, use the CSS border-spacing property on the table element:

Example

```
table {  
    border-spacing: 30px;  
}
```

## **HTML Table - Cell Padding**

Cell padding is the space between the cell edges and the cell content.

By default the padding is set to 0.

To add padding on table cells, use the CSS padding property:

Example

```
th, td {  
    padding: 15px;  
}
```

Add padding to the other sides with the padding-bottom, padding-left, and padding-right properties:

Example

```
th, td {  
    padding-top: 10px;  
    padding-bottom: 20px;  
    padding-left: 30px;  
    padding-right: 40px;  
}
```